

Windows Updates Validation Status.

- To find out which version of Windows your PC is running, press **Windows logo key + R**, type **winver**, then select **OK**.
- To view the update history on [Windows 10](#) : *Start Menu > Windows Settings > Update & security> Windows Update*. Click on the "**Update history**".
- Please note if you're using third-party software, plugins and/or hardware, you should check the respective manufacturer's information for their compatibility.
- Your OS version can be found in Windows Settings > System > About.
- Applying windows updates can sometimes be long, make sure you have some time to perform the update.

All Windows version mentioned are Pro Editions, and 64 bits, Windows 32 bits versions are no longer supported. Windows 10 is compatible since Pyramix v11-VCube v7-Ovation v7-AMR v7-RAVENNA ASIO driver V11.

As of July 2021, this list will only list the problematic updates. Please note that testing the updates can take several days after it has been released, please defer the updates as [described in this page](#).

The previous updates status page is now legacy and won't be updated, [but can still be accessed here](#).

- [Windows 11 21H2](#)
- [Windows 10 November 2021 Update 21H2](#)
- [Windows 10 May 2021 Update 21H1](#)
- [Windows 10 Fall 2020 Update 20H2](#)
- [Windows 10 May 2020 Update 2004](#)
- [Windows 10 November 2019 Update 1909](#)
- [Windows 10 May 2019 Update 1903](#)
- [Windows 7 SP1](#)

Windows 11 21H2

Supported since **Pyramix 14.0.3 / Ovation 10.0.3 / AMR 14.0.3 - NATIVE ASIO ONLY - MASSCORE CURRENTLY NOT COMPATIBLE**

Update Number	OS version	Availability date	Merging software version	Comments
Currently no updates issue			MassCore : Currently not compatible Native : PMX 14.0.3 / Ov 10.0.3	MassCore : Currently not compatible

Windows 10 November 2021 Update 21H2

Supported since **Pyramix 14.0.1 / Ovation 10.0.1 / VCube 10.0.1 / AMR 14.0.1**

Update Number	OS version	Availability date	Merging software version	Comments
Currently no updates issue			MassCore : PMX 14.0 / Ov 10.0 Native : PMX 14.0 / Ov 10.0	MassCore RTX 3.7.4 required

Windows 10 May 2021 Update 21H1

Supported since **Pyramix 25th Hotfix 3 / Ovation 9.0.6 / VCube 9.0.6 /AMR 13.0.6**

Update Number	OS version	Availability date	Merging software version	Comments
Currently no updates issue			MassCore : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0 Native : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0	MassCore RTX 3.7.4 required

Windows 10 Fall 2020 Update 20H2

Supported since **Pyramix 25th Hotfix 3 / Ovation 9.0.6 / VCube 9.0.6 /AMR 13.0.6**

Update Number	OS version	Availability date	Merging software version	Comments
---------------	------------	-------------------	--------------------------	----------

Currently no updates issue			MassCore : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0 Native : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0	<u>MassCore RTX3.7.4 required</u>
----------------------------	--	--	--	-----------------------------------

Windows 10 May 2020 Update 2004

Supported since **Pyramix 25th Hotfix 3 / Ovation 9.0.6 / VCube 9.0.6 /AMR 13.0.6**

Update Number	OS version	Availability date	Merging software version	Comments
Currently no updates issue			MassCore : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0 Native : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0	<u>MassCore RTX3.7.4 required</u>

Windows 10 November 2019 Update 1909

Supported since **Pyramix 12.0.5 / Ovation 8.0.5 / VCube 8.0.5 /AMR 12.0.5**

Update Number	OS version	Availability date	Merging software version	Comments
			MassCore : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0 Native : 25th Hotfix 3 - 14.0 / Ov 9.0.6 - 10.0	<u>MassCore RTX3.7 required</u>

Windows 10 May 2019 Update 1903

Supported since **Pyramix 12.0.5 / Ovation 8.0.5 / VCube 8.0.5 /AMR 12.0.5**

Update Number	OS version	Availability date	Merging software version	Comments
Microsoft end of service December 8, 2020				
No updates issues			MassCore : 12.0.5/ 8.0.5 Native : 12.0.4-12.0.5 / 8.0.4-8.0.5	<u>MassCore RTX3.7 required</u>

Windows 7 SP1

KB890830 and KB915597 are both Windows antivirus definitions updates, so it has no influence on Pyramix and can be installed.

KB2952664 is a telemetry service to Microsoft, you can skip / hide this update.

Update Number	Availability date	Merging software version	Comments
	1/14/2020		End of Microsoft official support https://support.microsoft.com/en-us/help/4057281/windows-7-support-ended-on-january-14-2020